

# Constants in LibreOffice BASIC

The Constants listed below were extracted from the LibreOffice source file:

/libreoffice-core-3.6.2.2/basic/source/runtime/stdobj.cxx

(For additional Constants available with "Option VBASupport 1" see the file:

/libreoffice-core-3.6.2.2/basic/source/comp/parser.cxx)

Name of Constant	Type	Value	Name of Constant	Type	Value
ATTR_ARCHIVE	integer	32	TYP_CHAPTERFLD	integer	4
ATTR_DIRECTORY	integer	16	TYP_CONDTXTFLD	integer	27
ATTR_HIDDEN	integer	2	TYP_DATEFLD	integer	0
ATTR_NORMAL	integer	0	TYP_DBFLD	integer	19
ATTR_READONLY	integer	1	TYP_DBNAMEFLD	integer	3
ATTR_SYSTEM	integer	4	TYP_DBNEXTSETFLD	integer	24
ATTR_VOLUME	integer	8	TYP_DBNUMSETFLD	integer	25
CF_BITMAP	integer	2	TYP_DBSETNUMBERFLD	integer	26
CF_METAFILEPICT	integer	3	TYP_DDEFLD	integer	14
CF_TEXT	integer	1	TYP_DOCINFOFLD	integer	18
CLEAR_ALLTABS	integer	2	TYP_DOCSTATFLD	integer	6
CLEAR_TAB	integer	1	TYP_EXTUSERFLD	integer	30
Empty	variant		TYP_FILENAMEFLD	integer	2
False	bool	False 0	TYP_FIXDATEFLD	integer	31
FRAMEANCHORCHAR	integer	15	TYP_FIXTIMEFLD	integer	32
FRAMEANCHORPAGE	integer	1	TYP_FORMELFLD	integer	10
FRAMEANCHORPARA	integer	14	TYP_GETFLD	integer	9
IDABORT	integer	3	TYP_GETREFFLD	integer	13
IDCANCEL	integer	2	TYP_GETREFPAGEFLD	integer	36
IDNO	integer	7	TYP_HIDDENPARAFLD	integer	17
IDOK	integer	1	TYP_HIDDENTXTFLD	integer	11
IDRETRY	integer	4	TYP_INPUTFLD	integer	16
IDYES	integer	6	TYP_INTERNETFLD	integer	37
MB_ABORTRETRYIGNORE	integer	2	TYP_JUMPEDITFLD	integer	38
MB_APPLMODAL	integer	0	TYP_MACROFLD	integer	15
MB_DEFBUTTON1	integer	0	TYP_NEXTPAGEFLD	integer	28
MB_DEFBUTTON2	integer	256	TYP_PAGENUMBERFLD	integer	5
MB_DEFBUTTON3	integer	512	TYP_POSTITFLD	integer	21
MB_ICONEXCLAMATION	integer	48	TYP_PREVPAGEFLD	integer	29
MB_ICONINFORMATION	integer	64	TYP_SEQFLD	integer	23
MB_ICONQUESTION	integer	32	TYP_SETFLD	integer	8
MB_ICONSTOP	integer	16	TYP_SETINPFLD	integer	33
MB_OK	integer	0	TYP_SETREFFLD	integer	12
MB_OKCANCEL	integer	1	TYP_SETREFPAGEFLD	integer	35
MB_RETRYCANCEL	integer	5	TYP_TEMPLNAMEFLD	integer	22
MB_SYSTEMMODAL	integer	4096	TYP_TIMEFLD	integer	1
MB_YESNO	integer	4	TYP_USERFLD	integer	20
MB_YESNOCANCEL	integer	3	TYP_USRINPFLD	integer	34
Nothing	object		V_EMPTY	integer	0
Null	null		V_NULL	integer	1
Pi	double	3.14159...	V_INTEGER	integer	2
SET_OFF	integer	0	V_LONG	integer	3
SET_ON	integer	1	V_SINGLE	integer	4
SET_TAB	integer	0	V_DOUBLE	integer	5
TOGGLE	integer	2	V_CURRENCY	integer	6
True	bool	True -1	V_DATE	integer	7
TYP_AUTHORFLD	integer	7	V_STRING	integer	8